

Moving Your T.O.M. Databases to a Different Server


Moving your T.O.M. Field Trip Database Files to a different server is a simple process. You only have to move the following four database files:

- 1. trip.mdb
- 2. tripschl.mdb
- 3. tripcal.mdb
- 4. gktmsc1.mdb

After moving these files simply reattach the T.O.M. software on each workstation to the new location. When running the attach utility uncheck the Use Old Path Check Box and click on the Attach button and browse to the new path. After that you should be good to go.

Of course, it's a different matter when setting this up with Remote Desktop. If you have any other questions or need additional information please don't hesitate to contact Gecko Microsolutions.


** NOTE: The new folder must be sure to give all users full authority to this folder.



Workstations with T.O.M. Software

Step 1 – Move Database Files to New Server





Workstations with T.O.M. Software

Step 2 - Reattach T.O.M. Software to New Server